



**PROCEDIMENTO DE REGISTRO DO SOFTWARE SOMOVE EM
COMPUTADOR SEM ACESSO A INTERNET.**

Ao abrir a janela para escolha da modalidade de registro do software selecionar a opção **“Ask for an authorization code”** e clicar em **“Next”**.

SoMove Lite - Registration Wizard

Select Task

Select the task to perform, and then click "Next".

☒ **Ask for an Authorization Code**
Select this option if you want to register SoMove Lite on this PC.

☐ **Transfer License Rights**
Select this option if you want to transfer the license rights to/from another PC or to another person.

☐ **Enter received Authorization Code**
Select this option if you want to enter your received Authorization Code now.

[View End-User License Agreement](#)

Help **Support** **Next >** **Cancel**



Na nova janela apresentada selecionar a opção ***“By e-mail”*** e clicar em ***“Next”***.

A screenshot of the "SoMove Lite - Registration Wizard" window. The window has a blue title bar and a light beige background. At the top right is the Schneider Electric logo. The main heading is "Select Registration Method". Below this are three tabs: "Immediate 24/7" (purple), "Quick" (green), and "Delayed" (orange). Under the "Quick" tab, there are five radio button options: "By web", "By phone", "By e-mail" (which is selected), "By web on another PC", and "By fax". Below the radio buttons is a text area with instructions: "Use this option if you don't need to get your Authorization Code back immediately. Your PC needs to be connected to the network. Press the button 'Next', complete the information, then the e-mail will be sent automatically. If the e-mail cannot be sent automatically, the e-mail content will be copied to the clipboard so that you can paste it into your e-mail program to send it manually. It will be processed during business hours of the call centers. You can expect an answer in the next two business days or sooner." At the bottom of the window are five buttons: "Help", "Print", "< Back", "Next >", and "Cancel".



Em seguida preencher a os campos obrigatórios do cadastro e clicar “**Next**”.

SoMove Lite - Registration Wizard

User Information
Required fields are marked with an asterisk.

First Name:	Rodolpho	*
Name:	Beazin	*
Company:	seb	*
Address 1:	Av Nacoes Unidas 18605	*
Address 2:		
Address 3:		
City:	Sao Paulo	*
State/Province:		
Country:	Brazil	*
Zip/Postal Code:	04753100	*
Use international format: Country Code - Area Code - Local Number, e.g. + 1 978 975 9755 (Numbers only. No spaces or dashes.)		
Telephone:	1 - 978 - 9759755	
Fax:	1 - 978 - 9759755	
E-mail:	rodolpho.beazin@schneider-electric.com	*
About Privacy		
Part Number:	SOMOVELITE	*
Serial Number:		E.g.: 21051234567

Help

Print


< Back

Next >

Cancel



Neste passo seleccionar o país para envio do e-mail.



SoMove Lite - Registration Wizard

Select E-mail Address

Please select the e-mail address of one of the following registration centers.

USA:	src-americas@schneider-electric.com
Czech Republic:	src-eeurope@schneider-electric.com
France:	src-weurope@schneider-electric.com

Buttons: Help, Print, < Back, Next >, Cancel

Após clicar em **“Next”** o assistente de registro tentará abrir o gerenciador de e-mail de seu computador. Como o computador em questão não possui acesso a internet será apresentada a mensagem de falha abaixo.



Registration Wizard

 **Registering Failure**

The e-mail could not be sent automatically but it was copied into the clipboard. Paste the content of the clipboard into your e-mail program and send the e-mail manually.

OK



Como o e-mail não pode ser enviado automaticamente os dados ficam armazenados na área de transferência de seu computador. Colar os dados em um documento e enviar o e-mail manualmente. Após isso clicar em ***“Finish”***.



Ao colar os dados armazenados na área de transferência será apresentado um arquivo semelhante ao da página seguinte.



TO: src-eeurope@schneider-electric.com

Subject: Product Authorization Code Request

PRODUCT: SoMove Lite Software

Version: 01.51

First Name: Rodolpho

Name: Beazin

Company: seb

Address 1: Av Nacoes Unidas 18605

Address 2:

Address 3:

City: Sao Paulo

State/Province:

Country: Brazil

Zip/Postal Code: 04753100

Telephone:

Fax:

E-mail: rodolpho.beazin@schneider-electric.com

Serial Number:

Part Number: SOMOVELITE

Code Entry Number: 324273032

Computer Id: 1838110



Ao receber o código de ativação selecionar a opção ***“Enter Received Authorization Code”*** e clicar em ***“Next”***.

The image shows a Windows-style dialog box titled "SoMove Lite - Registration Wizard". The title bar is blue with white text. The main area has a light beige background. At the top left of the main area is the text "Select Task". At the top right is the Schneider Electric logo. Below the logo, there is instructional text: "Select the task to perform, and then click 'Next'". There are three radio button options: 1. "Ask for an Authorization Code" with the subtext "Select this option if you want to register SoMove Lite on this PC." 2. "Transfer License Rights" with the subtext "Select this option if you want to transfer the license rights to/from another PC or to another person." 3. "Enter received Authorization Code" which is selected (indicated by a filled radio button) and has a dotted border around its text. Its subtext is "Select this option if you want to enter your received Authorization Code now." Below these options is a blue hyperlink that says "View End-User License Agreement". At the bottom of the dialog box, there are four buttons: "Help", "Support", "Next >" (which is highlighted with a darker border), and "Cancel".

Select Task

Select the task to perform, and then click "Next".

☐ Ask for an Authorization Code
Select this option if you want to register SoMove Lite on this PC.

☐ Transfer License Rights
Select this option if you want to transfer the license rights to/from another PC or to another person.

☒ Enter received Authorization Code
Select this option if you want to enter your received Authorization Code now.

[View End-User License Agreement](#)

Help Support Next > Cancel



Inserir o código de ativação no campo “**Received Authorization Code**”, clicar em “**Next**” e confirmar o registro de seu software.

SoMove Lite - Registration Wizard

Enter received Authorization Code 

Part Number:	SOMOVELITE
Serial Number:	---

Code Entry Number:	248245688
Computer ID:	1065595

Received Authorization Code:	
Received 2nd Authorization Code:	

[Help](#) [Print](#) [< Back](#) [Next >](#) [Cancel](#)